

Installing Pole Display with *PostalMate* software and Windows 7

Unpack the pole display and plug only the power cord in. Do not connect the USB cable until instructed.
Close *CashMate* & *PostalMate*.

1. Install correct driver.

- A. Go to OLSON & IVES and click on the driver.
- B. Click on **Open** and then **Allow** on the pop-up.
- C. A new window will open. Double click on *lcild_v207160*.
 1. Click **Run**.
 2. A wizard will open. Click **Next**.
 3. Keep the Installation folder location and make sure *Everyone* is selected. Click **Next**.
 4. Click **Next** to start Installation.
 5. Click **Yes** on the *User Account Control* pop-up.
 6. Click **Install** on the *Windows Security* pop-up.
 7. Click **Close**. Close the Window.

2. Install the display.

- A. Open **Devices and Printers**.
- B. Plug in the USB cable.
 1. The PC will install the device and list it under *Unspecified* when finished.
- C. Note the COM Port the device installed itself on.

3. Install the display as a printer.

- A. Click on **Add Printer** which opens the add printer wizard.
- B. Select **Add A Local printer**.
- C. Select *Use an Existing Port* and select the COM port you noted earlier. Click **Next**.
- D. In Manufacturer's box click **Generic &** in Printers box click **Generic/Text Only**. Click **Next**.
- E. Select *Use driver that is currently installed (recommended)*. Click **Next**.
- F. Type in *Pole Display* for the printer name.
- G. Click **Next**.
- H. Do not share the printer and click **Next**.
- I. Uncheck the box to set as the default printer.
- J. Click **Finish**.
- K. In *Devices and Printers* a printer named '*Pole Display*' should appear.
- L. Close the *Printers and Faxes* window.

4. Open *CashMate*.

- A. Select **Tools>Options>Register Settings**. Click on *Pole Display* tab.
- B. In *Enabled* section select **yes**. I
- C. In the '*Assigned Pole Display Device*' field click on the down arrow & select **Pole Display**.
- D. Hit the **TEST** button & whatever is under the default display appears on the pole display.
- E. Click **OK**. The main *CashMate* screen will appear.